

MISSION EDITOR

The manual assumes that you have to open the mission editor.

TIP: To switch between the manual and the editor, press left Alt+Tab keys.

NOTE: The abbreviations used here:

- LMB (an left mouse button)
- MMB (an middle mouse button, scroll wheel)
- RMB (an right mouse button)
- AI (an artificial Intelligence)

Contents

1. THE NORMAL MODE (2D)	1
1.1 Interface	2
1.1.1 Mission Parameters	2
1.1.2 Editing Modes	3
1.1.3 File Management	3
1.2 Basic Operation	4
1.3 Interacting with objects	6
1.4 Units	6
1.5 Groups	8
1.6 Triggers	8
1.7 Waypoints	11
1.8 Synchronization	17
1.9 Markers	18
1.10 Modules	19
1.11 Intel	20
2. THE ADVANCED MODE (2D/3D)	20
2.1 Interface	20
2.2 Centers And Groups	21
2.3 Units	21
2.4 Other Editor Objects	21
2.5 Editing A Unit	21
2.6 How to	22
2.7 Import of content	22
3. SCRIPTING	23

INTRODUCTION

The editor can operate in both normal and advanced mode:

- **Normal mode** allows the editing in two-dimensional (2D) space.
- **Advanced mode** allows the editing in both two-dimensional (2D) and three-dimensional (3D) space.

To create a mission (scenario), you need add content (objects) into a terrain. When the editor is started the map is empty, no mission objects are placed on.

NOTE: A new (empty) mission starts by default.

1. THE NORMAL MODE (2D)

Accessing The Editor

In the *Singleplayer* mode of a game:

1. In *Main menu*, select *Singleplayer* mode
2. In *Singleplayer* menu, select *Editor*
3. In *Select map* menu, select a map
4. Click the *Continue* button.

In the *Multiplayer* mode of a game:

1. In *Main menu*, select *Multiplayer* mode
2. In *Network games on Internet* combo box, click *New* button
3. In *Create game* dialog box, click *OK* key
4. In *Create game* combo box:
 - In *Difficulty* section, leave a default value;
 - In *Map* section, select a map;
 - In *Mission* section, select the <<*New – Editor*>> item
 - Click *Play* button

NOTE: There, the <<*New – Wizard*>> item invokes the editor to work with the game templates.

The editor operates likely in both *Singleplayer* and *Multiplayer* modes.

The difference is the mission preview:

- When in the *Singleplayer* mode, you is viewing from the perspective of a ***first person***.
- When in the *Multiplayer* mode, you will go into *Multiplayer Setup* combo box where you have to click *OK* button.

1.1 Interface

The interface of the editor is divided into two sections:

- At a left side the map section is. It displays objects placed.
- At the right side the control section is:
 - the mission parameters
 - the editing modes
 - the file management

1.1.1 Mission Parameters

- **The untitled menu** allows to choice a mission component for editing.
NOTE: All objects and parameters of the mission for the *Intro* and *Outro* cut scenes store separately from the mission. Therefore, you can do not use both the *Intro* and *Outro* components.
NOTE: Each component requires a unit controlled by player to be placed. A player controls his unit in the *Mission* component, and AI controls the player unit in both the *Intro* and *Outro* components. The *Intro* and *Outro* do not end when the player unit died, but can be ended using an end trigger.
The mission components:
 - ***Mission*** is set by default.
 - ***Intro*** acts before the briefing screen.
 - ***Outro - Win*** acts after the debriefing screen if one of six *Win* triggers activated.
 - ***Outro - Lose*** acts after the debriefing screen if *Lose* trigger activated.
- ***INTEL*** dialog box allows:
 - To name a mission
 - To brief describe a mission
 - To set starting date and time to the mission
 - To set current and forecast weather to the mission
 - To set friendly sides to *Independent*

1.1.2 Editing Modes

Each editing mode allows the creation and manipulation the one of the object types.

To set editing mode you can click a mode option or press the associated function key on the keyboard.

The modes are set out in the basic order they would be used while creating a mission:

- **Units (F1 key)** - the creation and manipulation these.
- **Groups (F2 key)** - the creation and manipulation of the unit groups and of the links between the units, also the manipulation of the links between the units and some other objects.
- **Triggers (F3 key)** - the creation and manipulation these.
- **Waypoints (F4 key)** - the creation and manipulation these for a selected unit (a unit group).
- **Synchronize (F5 key)** - the synchronization of waypoint-to-waypoint and waypoint-to-triggers types.
- **Markers (F6 key)** - the creation and manipulation these.
NOTE: The markers are visible while *Markers* mode.
- **Modules (F7 key)** - the creation and manipulation these.

1.1.3 File Management

- **Load** – the loading of a mission from directory: %user profile%\Arma 2\missions.
- **Merge** – the importing of the objects into the loaded mission from other mission.
NOTE: *INTEL* settings are not imported.
- **Save** – the saving of mission: name a mission and in the *Save as* menu select a way of saving:
 - **User mission** - the exporting of mission to directory: %user profile%\Arma 2\missions. These missions are only available via the mission editor.
NOTE: If mission is saved under a new name, only the *.sqm file will be written in the new folder. But if mission is saved under an existing name it also reloads other files in the folder.
 - **Export to single missions** - copying and packing of the mission to *.pbo file, and move it to the Program Files\Arma 2\Missions. This may be accessed from the *Main menu*.
 - **Export to multiplayer missions** - copying and packing of the mission to *.pbo file, and move it to the Program Files\Arma 2\MPmissions. This may be accessed from the *Main menu*.
 - **Send by e-mail** - copying and packing of the mission to *.pbo file, and loading of default email program using the file as an attachment.
- 1. **Clear** – the removing all objects (units, groups, triggers, waypoints, markers and modules).
NOTE: The *INTEL* settings are retained.
- 2. **IDs** – the switching on/off the numeric identifiers of the objects placed on the map with a map editor (*RTE Visitor*). They might be used to refer to these objects in script.
NOTE: The identifiers are hidden by default. These are visible at high zoom level.
- 3. **Textures** - the filling the terrain with the “satellite map”.
- 4. **Preview** – the mission preview with the game functions.
NOTE: The button appears lower *Texture* button once the player unit is created.
To end the preview:
 - Press *Esc* key
 - In *Paused* menu, click *Suspend (Abort)* button.**NOTE:** If *Shift* key is held down while clicking on the *Preview* button, the preview will include the briefing and debriefing screens.
NOTE: In *Multiplayer* mode the *Preview* button appears once the mission has been saved.
- 5. **Continue** – the resuming of the preview without changes. The button appears lower the *Preview* button after it is used.
NOTE: The changes made after you exited the preview will not be shown this a way. Instead, you must click the *Preview* button to restart with the changes.
NOTE: In *Multiplayer* mode the *Continue* button is absent.
- 6. **Exit**- the exiting of the editor.
NOTE: An unsaved work will be lost. Save it before.

1.2 Basic Operations

Edit Controls:

- **Pan** - hold down RMB and move the mouse.
- **Zoom** - roll the mouse wheel or press NumPad keys "+" / "-" .
- **Create (an object)** - double-click LMB on a map in the suitable editing mode.
- **Edit** - double-click LMB on an object.
- **Select** - one-click LMB on an object.
NOTE: Selected objects are opaque, and non-selected objects are slightly transparent.
- **Move an object** - hold down LMB on an object and move a mouse.
NOTE: It is not possible:
 - To move Units in *Groups* mode
 - To move Waypoints in *Synchronize* mode
- **Drag a selection box** –hold down LMB on empty space and move mouse over objects.
- **Add objects (to selected one)** –hold down *Ctrl* key and drag the selection box over the objects or individually by one-clicking LMB on each object.
- **Select objects associated with a group** –hold down *Shift* key and one-click LMB on a group leader or waypoint (if any).
- **Rotate** – hold down *Shift* key and hold down LMB on a selected object, and then move the mouse.
- **Select a waypoint-underlying object** –hold down *Shift* key and one-click LMB on an object with a waypoint attached to.
- **Edit the waypoint-underlying object** - hold down *Shift* key and double-click LMB on an object with a waypoint attached to.
- **Delete** - hover the mouse cursor on an object and press *Delete* key.
- **Cut**– select the objects and press *Ctrl + X* keys.
- **Copy** – select the objects and press *Ctrl + C* keys.
- **Paste**– place the mouse cursor where you want and press *Ctrl + V* keys.
NOTE: Names of pasted objects automatically get indices to avoid conflicts.
- **Paste the object on original position** –press *Ctrl + Shift + V* keys.
NOTE: It is useful when copying objects from a mission to other one.

Creating Units

A mission needs at least a unit controlled by a player to be run. There can be one player unit per a mission. A playable unit can be controlled by both a player and AI. There can be any number of the playable units per mission.

To create the player unit:

1. Select *Units* mode (**F1** key)
2. Double-click LMB on the map
3. In the *Insert Unit* dialog, set the *Side*, *Faction*, *Class*, and *Unit*
4. In the *Control* menu, select *Player*
5. Click *OK* button

NOTE: Here you may customize the settings *Rank*, *Special* and *Initialization* (see *Settings for Units*).

Unit Parameters

Name field represents referring to a unit via a script (global variable).

Description field represents a text in a networking lobby (in *Multiplayer* mode).

Side option:

- *BLUFOR* - opposites to *OPFOR* by default
- *OPFOR* - opposites to *BLUFOR* by default
- *Independent* - can be opposite to *BLUFOR*, *OPFOR* or both.
NOTE: The side is friendly to *BLUFOR* by default.
- *Civilian* – a satellite of the *Independent* and can be opposite to *BLUFOR*, *OPFOR* or both.
NOTE: The side is friendly to *BLUFOR* and *OPFOR* by default.
- *Game Logic* – a side of formal units which can be used for scripting.
NOTE: The formal units cannot act like normal units.
- *Empty* – the side of insentient units.
NOTE: This menu item appears after the player unit is created.

Control option:

- *Non Playable* - the unit is controlled by AI and is not selectable in the networking lobby.
NOTE: *Non Playable* unit has no circle surrounding.
- *Player* - the unit is controlled by a player and is selectable in the networking lobby.
NOTE: *Player* unit has a red circle surrounding.
- *Playable* - the unit is controlled by both a player and AI, and is selectable in the networking lobby.
NOTE: *Playable* unit has a purple circle surrounding.

Preview Mission

Once you have created a player unit you can preview the mission by clicking the *Preview* button.

The preview varies depending on the game mode:

- In the *Singleplayer* mode, preview allows see from the first-person perspective.
To get back to the mission editor from the preview:
 1. Press the *Esc* key
 2. In the *Paused* menu, select the *Suspend (Abort)* button
- In the *Multiplayer* mode, the preview first displays the role assignment screen.
NOTE: In the *Multiplayer* mode, to preview you have before to save the mission.
To get back to the mission editor from the preview:
 1. Press the *Esc* key
 2. Select *Suspend (Abort)* button
 3. Navigate back to the *Create game combo* box
 4. Select the desired mission
 5. Click *Edit* button.

Saving and Loading Mission

To save the mission:

1. Click *Save* button
2. Name the mission (if it is not already named)
3. Select a way for a saving
4. Click *OK* button

The save way determines where the mission will be available from:

- **User mission** (by default, for the mission editing only): The mission will be saved into `%UserProfile%\My Documents\Arma 2 \missions` (for Windows XP).
- **Export to single missions** (for *Singleplayer* game mode): The mission will be saved into `%UserProfile%\My Documents\Arma 2 \missions`, but will also be copied to `%Arma 2 installation%\Missions`. The exported mission is saved as compressed ***.pbo** file. The mission can be accessed from the *Main menu > Scenarios > Single Missions* combo box.
- **Export to multiplayer missions** (for *Multiplayer* game mode): The mission will be saved into `%UserProfile%\My Documents\Arma 2 \missions`, but will also be copied to `%Arma 2 installation%\MPmissions`. The exported mission is saved as compressed ***.pbo** file.

- **Send by e-mail:** The mission will be saved into %UserProfile%\My Documents\Arma 2 \missions, but will also be copied to %Arma 2 installation%\Missions. The exported mission will have been sent by default e-mail service as attachment to.

To load a mission:

1. Click *Load* button
2. Select a map
3. Select a mission
4. Click *OK* button

1.3 Interacting with objects

Copy and Paste

1. One-click LMB an object
2. Press *Ctrl + C* keys
3. Set the mouse cursor where you want
4. Press *Ctrl + V* keys

Move

1. One-click LMB an object
2. Hold down LMB on it and move a mouse

Rotate

1. One-click LMB an object
2. Hold down the left Shift key + hold down RMB
3. Move the mouse

NOTE: It is only possible in the *Units* mode

NOTE: To select several objects you can use two ways:

- One-click LMB an object, hold down the left *Ctrl* key and one-click LMB another object.
- Hold down LMB and draw a selection box over objects.

Edit

To edit you have to double-click LMB on an object.

NOTE: The data that you put into the dialog fields are saved in *.sqm file. To edit it you have to exit the editor.

1.4 Units Mode

The *Units* mode is used to create and manipulate units:

- To create a unit, double-click LMB on the map where you want. An *Insert unit* dialog will open.
- To edit a unit, double-click LMB on this. An *Edit unit* dialog will open.

NOTE: It is not possible to edit a unit in the *Waypoints* mode.

Unit settings:

- **Side**
 - **BLUEFOR** – the side opposites to *OPFOR* by default
NOTE: The units are represented by the blue icons
 - **OPFOR** – the side opposites to *BLUEFOR* by default
NOTE: The units are represented by the red icons.
 - **Independent** – the side may opposite to *BLUEFOR*, *OPFOR* or both.
NOTE: It is friendly to *BLUEFOR* by default. The *Independent's* relations with *BLUEFOR* and *OPFOR* can be set via the *Intel* dialog. These units are represented by the green icons
 - **Civilian** – the satellite of the *Independent* and can opposite to *BLUEFOR*, *OPFOR* or both.
NOTE: It is friendly by default to both *BLUEFOR* and *OPFOR*. The *Civilian* can inherit the friends and enemies of the *Independent*. The units are represented by the yellow icons.
 - **Ambient life** – the side of natural units.

- **Game Logic** – the side of formal units that among other uses can be used for scripting. The formal units cannot act like normal units.
NOTE: This menu item appears once the player unit is created.
- **Empty** – the side of insentient objects. It includes empty vehicles and other objects.
NOTE: This menu item appears once the player unit is created.

The side of a unit defines the available options.

NOTE: It is not possible to change the side of unit once it has been created, but with script.

- **Class** - it defines the class of a unit.
- **Control** - it defines a controller of a unit.
NOTE: If a unit is a vehicle, extra options are available.
NOTE: The option is not available for *Game Logic* and *Empty* sides.
 - **Non Playable** - the unit is only controlled by AI.
NOTE: The non-playable units are marked by icon without circular.
 - **Player** - the unit is only controlled by player. There can only be single player unit per a mission. The player unit is marked by red circular.
NOTE: The player control of vehicle is different from one of the man:
Player as Pilot/Driver/Gunner/Commander – the specified position will be playable by the player.
 - **Playable** - the unit is controlled by player (via *Team Switch* (T key)) and by AI. Playable units are marked by magenta circular.
NOTE: The playable control of vehicle is different from one of the man:
Playable as Pilot/Driver/Gunner/Commander – the specified position will be playable by the player.
NOTE: To place an empty vehicle you need to select *Empty* side.
NOTE: If the vehicle is an **unmanned air vehicle (UAV)**, then you need to set the *Special* setting to *Flying*. The unmanned vehicles have a crew of invisible units controlled by AI in the driver and gunner positions. Therefore an unmanned vehicle can be controlled through waypoints like a manned vehicle.
- **Info age** – it defines how long a unit has been unknown since some unit belonging to the same side as player has seen it. Units are unknown (by default) unless enemy sees them (*Unknown*). This way you can reveal enemy unit to a side (*Center*) of the player.
- **Vehicle lock** – it is only functional for an empty vehicle. It defines whether a player group can board the vehicle.
NOTE: The player group's leader controlled by AI does not understand that a player cannot enter a locked vehicle. Scripting commands will not respect this setting.
- **Rank** - it defines the unit rank. The highest ranking unit in a group will normally be its leader. Rank has some effect on a behavior - highly ranked units will be less likely to flee and also will be more intimidating to enemy.
- **Unit** - it defines the unit type.
NOTE: The option depends on the **Class**.
- **Special** – it defines the start position of the unit:
 - **None** – the unit is placed at a specified position.
NOTE: The unit will be created in the nearest empty location to avoid collision.
 - **In Cargo** - if the group possesses a vehicle with empty cargo seats the unit will be placed in one of these.
NOTE: If no cargo seats are available, it will be created at the specified position.
 - **Flying** – the flying vehicles (planes and helicopters, UAV) will be created in the air.
 - **In Formation** - the unit will be created in formation around a group leader, irrespective of the specified position.
- **Name** – the field is used to access the unit via script. Like variable names, it must be unique and not contain any spaces or reserved characters.
- **Skill** - it defines a skill level of a unit.
- **Initialization** – it can contain a script that is executed at the start of the mission. A reference to a unit itself is passed to the code as the variable **this**.
TIP: You can quickly move the cursor through the field by holding the left **Ctrl** key and press **Left/Right Arrow** key.

- **Description** - it is a text displayed next to the unit in the networking lobby.
- **Health/armor** – it defines man health/vehicle armor.
NOTE: The value of 0 means a man is dead/a vehicle is destroyed.
- **Fuel** – it defines the fuel amount of a vehicle.
- **Ammunition** – it defines the ammunition amount of a man.
NOTE: A unit with an ammo value of 0 has no ammunition.
- **Azimuth** – it defines the direction of a unit facing. It is possible to point around the circle by one-click LMB or enter the value directly into its own box.
NOTE: If the unit is set *In Formation*, then it uses the direction of a group leader's facing.
- **Probability of presence** – it defines a chance the unit will be created in the mission.
- **Condition of presence** – it evaluates the value to either **true** or **false**.
NOTE: If value of **false**, then the unit will not be created.
- **Placement Radius** – the field defines the radius of a circle in which the unit is randomly placed.

1.5 Groups Mode

The *Groups* mode is used to create and manipulate the unit groups and links between the units.

To create a group:

1. Select the *Groups* mode (F2 key)
2. Double-click LMB on the map
3. In the *Insert Groups* dialog box, select the side, faction, type, name, and facing direction.

NOTE: Placing units near one-by-one in the *Units* mode automatically link them together.

To create a link between units:

1. Select the *Groups* mode (F2 key)
2. Hold down LMB on the unit to link from
3. Move mouse to another unit to link to
4. Release LMB

- The link is represented by a blue line.
- The linking of a unit can only be by one way, either link **to** or **from** the unit.

To remove a link between units:

1. Select the *Groups* mode (F2 key)
2. Hold down LMB on a unit to remove the link from
3. Move mouse to an empty space on the map
4. Release LMB

1.6 Triggers Mode

A **trigger** is an object that waits until a *Condition* is **true** and then carries out an action.

NOTE:

- It is represented by a blue ellipse or rectangle with a small blue flag at the centre.
- The location and dimensions of a trigger are not always relevant.
- A trigger may be linked with a unit so that only this unit can activate it.
- A trigger can be used to return a list of objects that satisfy the activation condition.
- The activation condition is checked approximately two times per second.

To create a trigger:

1. Select the *Trigger* mode (F3 key)
2. Double-click LMB on the map

Trigger settings:

- **Axis "a"** (horizontal), **Axis "b"** (vertical) - the dimensions of the trigger area in meters.
NOTE: This assumes that the trigger has not been rotated.
- **Angle** – the rotate angle in degrees.
Example: "0" faces north, "90" faces east, "180" faces south, "270" faces west.

To rotate a trigger:

1. Hover a mouse cursor on the trigger flag
 2. Hold down *Shift* key + hold down LMB
 3. Move a mouse.
- **Ellipse/Rectangle** - the trigger shape.

- **Activation** – an activation condition.

NOTE:

- Some of these conditions cannot be efficiently created by script.
- This option determines a value of the variable **this** in the *Condition* field below.
- If the trigger is linked to a unit then only the relevant options will be available.

Activation conditions:

- **None** - the trigger will get the evaluation result in the *Condition* field to determine whether the *On Activation* code will be executed.
- **OPFOR/BLUFOR/Independent/Civilian** – the *Side* that can activate the trigger.
Example: If *Activation* is set to *OPFOR* the trigger will be activated when a unit of side *OPFOR* (*East*) enters the trigger area.
- **Game Logic** - this will activate the trigger.
- **Anybody** - this will activate the trigger.
- **Radio <radio_name>** –this will activate the trigger via *Radio* item of the action menu.
NOTE: The radio triggers can be reactivated without the deactivation of them.
- **Seized by OPFOR/BLUFOR/Independent** – the trigger will be activated when the seizing side is deemed to be in control of the area. This condition works with the *Timeout* option. A low level of presence will activate the trigger after a time closer to the maximum timeout, and vice versa. Depending on unit types, the seizing side can be completely outnumbered (4:1) and still satisfy the minimum level of presence for the maximum timeout.

Alternative options:

NOTE: These options are available if the trigger is linked to a unit.

- **Vehicle** - a trigger will be activated by the linked unit.
- **Whole Group** - a trigger will be activated by the group (with leader linked to the trigger).
- **Group Leader** - a trigger will be only activated by the group leader.
- **Any Group Member** - the trigger will be activated by any one.
- **Once/Repeatedly:**
 - **Once** – a trigger will remain active for the duration of the mission.
 - **Repeatedly** – a trigger can be reactivated after deactivation of it.
NOTE: Most of repeatable triggers can only be reactivated once they have deactivated.
- **Present / Not present:**

NOTE: To be considered present, an object must be alive (undestroyed).

 - **Present** - a trigger will be activated when an object matching the *Activation condition* is within the trigger area.
 - **Not present** - a trigger will be activated when an object matching the *Activation condition* is not within the trigger area.
- **Detected by <side_name>** – a trigger will be activated when a unit of the one side is detected by a unit of a specified side.
- **Countdown/Timeout (Min, Mid, Max)** - these counters determine a delay (in seconds) to the activation.
NOTE: If the *Min*, *Mid*, and *Max* values are different then a random value between them will be determined.
 - **Countdown** - once the trigger conditions are **true** the trigger will wait the specified time before activation.
 - **Timeout** - the trigger conditions must be met for the duration of the specified time before activation.

NOTE: if a unit enters into the area of a **side-present** trigger type but leaves this before the timeout is complete, the trigger will not activate.
- **Type** – it defines the effect types on activation and the abstract types that are generally unavailable via script. These events will take place immediately after the *On Activation* script has executed.
 - **None** –by default, the trigger will execute script in the *On Activation* field.
 - **Guarded by <side_name>** - the trigger will define a guarded array.
NOTE: A trigger must be linked to the unit for this type. The linked unit that has an active *Guard* waypoint will move to the first placed (highest priority) available unguarded point. If an

enemy is detected, the group guarding the lowest priority point will leave this to attack the enemy.

NOTE: The units controlled by AI will react over any distance, even if they are not capable of destroying the detected unit.

- **Switch** - the option is useful for "breaking" a group out of the *Cycle* waypoint, or moving the group away from a *Hold* or *Guard* waypoint. When the trigger is synchronized with a waypoint, activating the trigger will change the unit's current waypoint to the next waypoint from the synchronized one.

NOTE: *On Activation* script of the synchronized waypoint is not executed.

- **End # (1–6)** – these will end the mission once the trigger conditions are met.

NOTE: Each of the 6 win ends can be with a different debriefing.

- **Lose** – this will end the mission in failure.

NOTE: This only affects the debriefing.

- **Name** – it defines the trigger name for script. It must comply with variable name rules (no spaces, no reserved characters or words, and no duplicate).
- **Text** - it can replace the default name of the radio in the action menu and on the map.
NOTE: In the mission editor, this is displayed when the mouse cursor is on the trigger.
- **Condition** - the trigger will activate when this returns **true** value.

NOTE:

- The variable **this** refers to the *Activation condition* above.
- The variable **thisList** refers to units that are met the *Activation condition* within the area.

NOTE: The **thisList** does not always refer to units that are activating the trigger:

- If the *Activation condition* is not side related, **thisList** will return an empty list (array)
- The **seized-by** trigger type will return units of any side.

NOTE: If the *Condition* field is blank, the trigger will never activate. Using a script-based *Condition* allows the creation of complex *Activation*, including AND/OR conditions.

- **On Act (On Activation)** - the script will be executed when the trigger conditions are met.

NOTE: Any actions defined by the *Type* will take place immediately after this begins.

- **On Dea (On Deactivation)** – the script will be executed when a *Condition* of a repeatable trigger returns **false** value after having been previously **true**.

NOTE: The *Radio* trigger does not deactivate, and never executes the *On Deactivation* script.

- **Effects** – (see *The Trigger and Waypoint Effects* below)

To link units to triggers:

1. Select *Groups* mode (F2 key)
2. Hold down LMB on the unit to attach from and move the mouse cursor to the trigger to attach to.

1.7 Waypoints Mode

The **waypoint** is used:

- To move the units controlled by AI
- To indicate where a player has to move

NOTE: The waypoint is added to a unit group, not to the unit itself.

To create a waypoint:

1. Select the *Waypoints* mode (F4 key)
2. One-click LMB on a single unit or a group leader to add a waypoint to
3. Double-click LMB where you want to create the waypoint
4. In the *Insert waypoint* dialog box, adjust the settings
5. Click *OK* button

NOTE: Once first waypoint has been created the next waypoint will be linked to this.

To delete a waypoint:

1. Hover the mouse cursor over the waypoint
2. Press the *Delete* key

NOTE:

- If waypoints are added to a single unit or a group leader controlled by AI, the units will follow the allocated path.
- If waypoints are added to a single unit or a group leader controlled by a player, the player will see a waypoint indicator in a game.

The waypoint settings:

- **Select type** – the action that will be done when a unit controlled by AI reaches the waypoint.
NOTE: Some waypoints allow link to the other objects to define behavior (see *Waypoint Types*).
- **Waypoint order** - the order number of the waypoint. You can use it to insert a waypoint between existing waypoints or change the order of existing waypoints.
NOTE: The order numbering of waypoints on the map is different to the index numbering of waypoints in the script. The start position of a unit has no order number, but has the index number of 0. The first added waypoint has the order number of 0 and the index number of 1, and so on.
- **Description** – the text when a player has allocated a waypoint.
NOTE: If this field is blank, the waypoint type is displayed.
- **Combat Mode** – it defines whether units controlled by AI will engage enemy:
 - **No change** - the group keeps its current mode.
 - **Never fire (BLUE)** - the leader will order his group to hold fire and disengage. The units will not fire on an enemy under any circumstances.
 - **Hold fire (GREEN)** - the leader will order his group to hold fire and disengage. Individual units can open fire on an enemy that is a threat.
 - **Hold fire, Engage at will (WHITE)**, the leader will order his group to hold fire, but engage enemy at will. Individual units can open fire on an enemy that is a threat.
 - **Open fire (YELLOW)**, by default - the leader will order his group to engage the enemy. Units will fire upon suitable targets, staying in formation.
 - **Open Fire, Engage at will (RED)** - the leader will order his group to engage upon suitable targets and move out of formation.

NOTE: Above rule for a group behavior holds for a single unit.

- **Formation** – it defines a formation that units controlled by AI will adopt:
 - **No change** - the group keeps the current formation.
 - **Column** - the group forms into column behind the group leader (unit 1).
 - **Staggered Col.** - the group forms into two columns. The right column is staggered behind the left, and the group leader (unit 1) is placed at the forward of the left column.
 - **Wedge** – the group forms into a wedge (by default), with unit 1 at the forward. Each following unit will tab an equal distance behind and to the left or right from the unit in front: odd units on the left, and even units on the right.
 - **Echelon L.** - the group forms into a line behind and to the left of the group leader (unit 1).
 - **Echelon R.** - the group forms into a line behind and to the right of the group leader (unit 1).
 - **Veer** - the group forms into an inversed wedge (see above).
 - **Line** - the group forms into a perpendicular line to the facing direction of the group leader.
 - **Delta** - the group forms three columns behind unit 1.
 - **Column (compact)** - the group forms into more compact column behind the group leader.
- **Speed** – the speed for units controlled by AI.
NOTE: The speed is set when a unit leaves a waypoint, not when a unit comes into a waypoint.
NOTE: In *Normal* or *Limited* speed mode, the leader will move at a slower rate to allow his group to maintain formation. A leader in an aircraft will probably not be able to move slowly enough to allow ground units to keep up:
 - **No change** – the units stay move at their current speed.
 - **Limited** – the units move at a low speed.
 - **Normal** (by default) – the units move at a moderate speed.
 - **Full** – the units move as quickly as possible.
- **Behavior:**
 - **No change** – the units stay in the current behavior.
 - **Careless** – the behavior is non-combat. The group forms the compact column-like formation, where each unit will directly follow the one in front, rather than the group leader. Infantry will carry their weapons in safe position (rifles across body, pistols holstered) and walk. Infantry will not fire on enemy (unless they are shot at), but vehicles will still fire on enemy. Units do not switch to a more alert mode if enemies are encountered. Units prefer move along roads whenever possible.
 - **Safe** – this is similar to the **Careless** mode, but units change behavior to *Aware* upon detecting an enemy.

- **Aware** (by default) - The infantry moves at moderate speed, with units generally standing upright and making some occasional efforts to use cover when available. Most units prefer to travel along roads and travel in convoy irrespective of formation type. Tracked vehicles do not use headlights, and drive beyond of roads. Helicopters do not use searchlights. When enemies are known, infantry disembark from any transport (trucks, cars), and move carrying out bounding maneuvers, using available cover.
- **Combat** – the infantry always move using bounding maneuvers, and normally keep crouched or prone unless moving. They make some use of available cover, choosing to spend some time crawling when in cover. They occasionally send out one unit ahead of the group as a scout. The vehicles do not use headlights at night. If enemy are known, infantry moves in a more cautious manner. **NOTE:** This type overrides other movement settings (*Combat Mode, Formation and Speed*).
- **Stealth** – the infantry moves via cover whenever possible, spending much of time crawling. When they need to cross open ground, they occasionally choose to send scouts running ahead to reach the cover ahead as quickly as possible. A stealthy infantry formation can tend to end up quite fractured. Wheeled vehicles follow roads available, but no longer convoy. If enemy are known, infantry moves more closely together and spend more time prone.
- **Placement Radius** – the area where the waypoint is placed at random within the radius, in meters.
- **Completion Radius** – the area where a unit is desired as entered within the radius, in meters.
- **Position in house** – the list of the positions in a building. **NOTE:** The option only appears in the *Waypoints* mode and a mouse pointer is placed over building so that a house name appears.
- **Timeout (Min, Mid, Max)** – the time that the units controlled by AI will wait before moving to the next one. **NOTE:** If values vary then a random time (between *Max* and *Min* values) will be defined.
- **Condition** – the script that must to evaluate to **true** before the units controlled by AI will move to the next waypoint. In other words, the units controlled by AI will move to the waypoint and wait here until the script evaluates to **true**. **NOTE:** The variable **this** refers to the group leader and the variable **thisList** refers to all the group members.
- **On Act. (On Activation)** - the script executed when the waypoint is completed. Within the field the variable **this** refers to the leader and the variable **thisList** refers to all the group members.
- **Script** – it is only used if the waypoint is of the *Scripted* type (see *Waypoint Types*).
- **Never show/Show in cadet mode/Always show** - defines whether the waypoint is visible in a mission.
- **Effects** – (see *The Trigger and Waypoint Effects*)

Waypoint Types

The waypoint type defines what the AI units have to do when the waypoint becomes active.

MOVE - causes the units move to a location or object. This is completed when a unit or the group leader entered into the completion area. The radius of the completion area is from 1 to 500 meters depending on vehicle type and on the unit control (by AI or player). The movement depends on the behavior. If the next waypoint is far enough away, then a group boards its own vehicles (if any).

NOTE: If the waypoint is too far away or a valid path cannot be found, the units may never reach this.

DESTROY - causes the units destroy an object the waypoint is placed upon:

- If the waypoint is placed on an object of the same side that has to destroy, the waypoint will be considered complete.
- If the units are incapable of destroying the object, but consider it capable of being destroyed, they will wait until it is destroyed.
- If the units are incapable of destroying the object and consider it not possible to destroy, or of no interest (e.g., a tree, fence), the waypoint will be considered complete.

NOTE: If this type is placed spatially or on a non-target object, the units will attack a unit that happens to near the waypoint, irrespective of that unit's side.

GET IN - the effect of this depends on whether it is synchronized:

- If this is not synchronized, units will board their own vehicles with the free seats.
NOTE: This happens as the waypoint becomes active, rather than when it is reached. The units will not move to the actual *Get In* waypoint, but carry out the board then continue move on to the *Get In* waypoint.
- If the waypoint is synchronized with a waypoint of a friendly vehicle:
 - with the free seats, but the group has already enough free seats to fit the whole group, the units will move to the waypoint then the group will board the free seats of the friendly vehicle.
 - with some free seats, but not enough to allow the whole group to board, the leader will order as many units as possible to board the friendly vehicle.
 - with no free seats, the units will move to the waypoint, and then continue on to the next one.

SEEK AND DESTROY - It does not matter if the waypoint is placed spatially or on an object.

If the waypoint placed on an object, it will remain fixed at the displayed position of the object (even if the object actually starts the mission in the cargo of another vehicle or has its position changed by its *Initialization*).

Behavior is the same for both situations, the group will move to the waypoint, then the leader will move about to search the immediate area with his group trying to keep up.

The search area is limited to the leader's expected time of the search:

- A unit on foot will rarely search more than 50 m from the waypoint center.
- A unit in a vehicle will search up to 300 m from the waypoint center.

NOTE: The unit "visually" checks the search range so a search in a city will take longer time than in a field.

NOTE: The waypoint does not appear to make the units search in buildings although their path may lead them to enter some. Whether or not the units find the enemy appears to have no impact on the search duration or range.

JOIN – this has to be synchronized with a waypoint of another unit, the attached units will move to the attaching unit once they have achieved their "synchronized-to" waypoint, then join and follow that unit, irrespective of a side and rank.

The attached unit may have moved on, but the *JOIN* waypoint remains at the location when the waypoint became active.

NOTE: If the waypoint is not synchronized with, the units will treat it as a *MOVE* waypoint.

If the waypoint is synchronized with waypoint of another unit, when both groups are at their waypoints, the units of waypoint that is "synchronized-from" will join the units of waypoint that is "synchronized-to", irrespective of which group has the *JOIN* waypoint itself.

Only two groups can join via single *JOIN* waypoint.

To synchronize:

1. Click the *Synchronization* mode (F5 key)
2. Hold down LMB on the waypoint that is attaching
3. Move a mouse to the waypoint that is attached.
4. Release LMB

JOIN AND LEAD - the waypoint is like to the *JOIN* waypoint, except the attaching and attached units will be opposite in each time.

GET OUT - the units in their vehicles will move to the waypoint and disembark the members are in.

If the members, except the leader, are in another vehicle then this will stop to let them out.

NOTE: A possible complication occurs when the leader is riding in vehicle of another group. The *Get Out* waypoint will not be considered reached until the leader arrives at it under his own control (i.e., it will not complete until the leader is out of the vehicle).

If the *Get Out* waypoint is placed on an object, the units will move to the object location at the instant the *Get Out* waypoint becomes its current waypoint then normal disembark.

CYCLE - this switches the active waypoint to the nearest waypoint.

NOTE: The automatically created first waypoint (the initial position of a unit) is considered as a *Move* type and can be used by the *Cycle* waypoint, but you need have at least one more between these points. This type can be used to make the group move in a loop (to create a patrol). The *Switch* trigger can be used to "break" a group out of a cycle induced waypoint loop.

LOAD - the units will move to the waypoint then those on foot will board their own vehicles.

NOTE: They will get as the vehicle cargo and then as the vehicle crew.

UNLOAD - the units will move to the waypoint then those are in a vehicle cargo will disembark.

NOTE: Units in crew positions will not disembark.

TRANSPORT UNLOAD - the vehicle will move to the waypoint, where units of another group who are in vehicle cargo of the original group will disembark.

HOLD - the units will move to and stay at this waypoint.

NOTE: Only a *Switch trigger* or a *script* command will make the units to move from this waypoint.

SENTRY - the units will move to the waypoint and hold position until the group knows enough about units to identify which side these belong to, and that they are capable of attacking. At that point, the units will proceed to their next waypoint. They will also attack the spotted enemy on the way.

GUARD - this is used with the *Guarded by trigger* type. The units will move to the waypoint and wait for a point to require guarding. A point or object is only considered as guarded if a group has been set to guard it through a *Guard* waypoint (other friendly forces in the area are not considered). If there are several the *Guarded by* triggers, the group will move to the first placed (highest priority), unguarded trigger (or its linked object). Once at a guard point, the units will continue to check if a higher priority guard point requires guarding, or for an enemy to engage. A group can be made to stop guarding using the **setCurrentWaypoint** *script* command or a *Switch* trigger.

TALK - this is used with the *Effects* (see *The Trigger and Waypoint Effects* below). The leader will speak the given *Voice* phrase, complete with lip movements. The group does not need to move to the waypoint, instead skipping immediately to the next.

SCRIPTED – this executes the *script file* that is entered in the *Script* field in the *Insert/Edit waypoint* dialog. Enter the file name directly, without **exec** *script* command or quotation, and then enter up to 4 arguments in an array. This array is passed to the script in the form [**<unit>**, **<waypoint position (array)>**, **<object waypoint is attached to>**, **< element 0>**, **< element 1>**, **< element 2>**, **< element 3>**].

NOTE: The units will wait until the external script exits before moving on.

NOTE: The *On Activation* field can be used to execute the script.

SUPPORT - the units will move to the waypoint and then wait until they may provide support for other units that require relevant support using *Call Support* menu. At this time, the waiting units will move to the location where support is required for, disembark from their own vehicles and wait for the supported unit to declare *Support Done* before being able to respond to further requests for support.

NOTE: Only a medic (ambulance); ammo, repair and fuel vehicles can respond to the support requests. The first available one of the support units will respond first, irrespective of distance.

NOTE: The player units must announce *Support Done* to allow the support units to be able to support. AI leaders tend to request that every appropriate support unit attends them. AI will not take vulnerability of a support group into consideration when requesting support.

GET IN NEAREST - the units will only move to the waypoint if there are empty vehicles or vehicles on their side with the free seats that are within about 50 m of the waypoint area.

NOTE: The units will only fill free seats in the nearest vehicle.

DISMISSED – the units will simulate casual off-duty behavior. They will move to the waypoint then be dismissed. The group will split itself into smaller ones of from one to two units, who will move to random locations within about a 300 m radius, sit down, etc.

NOTE: The waypoint does not inherently alter behavior mode, nor make men disembark, land or turn vehicle engines off. The waypoint is considered complete if the group contacts with enemy.

AND – this is only available for units of the *Game Logic* side. The waypoint will complete when all waypoints it is synchronized with have been completed.

OR – this is only available for units of the *Game Logic* side. The waypoint will complete when one of the waypoints it is synchronized with has been completed.

NOTE: The units of the *Game Logic* side only have the types *AND* and *OR*.

The Trigger and Waypoint Effects

Effects are the same for a trigger and a waypoint. The **Effects** dialog box allows for audio and visual effects to be created when a trigger is entered (a waypoint is completed) or the *On Activation* script is executed.

NOTE: To open the *Edit effects* dialog box, press *Effects* button in the *Insert/Edit trigger (waypoint)* dialog:

- **Untitled condition field**
NOTE: This must evaluate to **true** (in addition to the main Condition) for the effect to be activated.
- **Anonymous** – a sound comes from everywhere
- **Voice** – a sound comes from the trigger position
- **Environment** – a sound comes from everywhere
- **Trigger** – a sound comes from the trigger position
- **Track** – music soundtracks
- **Type:**
 - **NONE** - self-explanatory
 - **OBJECT** - a predefined 3D object in front of the field of vision
NOTE: The effect is used to create the splash screen.
 - **RESOURCE** - a predefined graphical resource over the field of vision.
NOTE: The effect is used to display splash screen.
 - **TEXT** - the text typed in the untitled field below, with the style chosen in the *Effect* option.
NOTE: The effect is identical to the *cutText* scripting command.
- **Effect:**
 - **PLAIN** - displays the *Type* given (above).
 - **BOTTOM** - displays the *Type* given.
NOTE: This plain text is placed at the bottom of the screen.
 - **BLACK** - turns the screen to black, and displays the *Type* given. GUI is hidden.
 - **BLACK FADED** - turns the screen to black without fading in, and displays the *Type* given.
NOTE: If pause time is not given, the *curtain* and the displayed *Type* disappear after 5-10 sec.
 - **BLACK OUT** - turns the screen to black and displays the *Type* given. GUI is hidden.
 - **BLACK IN** - reveals the GUI after a black *curtain* is withdrawn along with the *Type* given.
 - **WHITE OUT** - turns the screen to white and displays the *Type* given. GUI is hidden.
CAUTION: This can blind the player.
NOTE: Make sure that a fade in time is set when calling the command.
 - **WHITE IN** - reveals the GUI after a white *curtain* is withdrawn along with the *Type* given.
 - **PLAIN WITHOUT FADING** - self-explanatory
- **Untitled text field** – the field can contain text which will display if the *TEXT* type has been selected from the *Type* option above.

1.8 Synchronization

Synchronization defines dependencies for the *waypoints* and *triggers* to control their execution.

Synchronization Types

Synchronizing	waypoint	trigger
waypoint	waypoint-to-waypoint	waypoint-to-trigger
trigger	trigger-to-waypoint	trigger-to-trigger

Synchronization is represented by a dark blue line.

To synchronize:

1. Select the *Synchronize* mode (F5 key).
2. Hold down LMB on the waypoint and move the mouse to other waypoint/trigger.
3. Release LMB.

To desynchronize:

1. Select the *Synchronize* mode (F5 key).
2. Hold down LMB on the waypoint/trigger and move the mouse into empty space on the map.
3. Release LMB.

NOTE: All the synchronizing links will be removed from the object.

Waypoint Activation

The synchronized waypoint will be activated when the other synchronized waypoints are active. This means that the *On Activation* code is not applicable while the synchronization.

If synchronization is of a **waypoint-to-waypoint** type, the AI units will move to the waypoint (even if the type would not involve moving to this).

NOTE: In game a player will see the synchronized waypoint as "Wait" type.

If synchronization is of a **waypoint-to-trigger** type, the units will wait at the waypoint until the trigger is activated.

NOTE: The trigger does not wait for waypoint to be activated, but the waypoint does.

The synchronization does not have a polarity. It does not matter which waypoint is **synchronized-from** and which is **synchronized-to**.

NOTE: With some waypoint types, such as *Get In* and *Join*, the synchronization has greater significance than timing. It defines which units shall join and which shall be joined.

The *Game Logic's OR* type is another case, it only requires one synchronized waypoint/trigger to be ready.

NOTE: It is possible to synchronize one waypoint with other waypoints of another group, or triggers.

1.9 Markers

The *Markers* mode is used:

- to place the *marker icons* and *zones* on the map
- to define a possible starting positions for other objects via a grouping markers and other objects.

NOTE: Markers are only visible in *Markers* mode, but can be manipulated in other modes.

To create a marker:

1. Select *Markers* mode
2. Double-click LMB on a map

To remove a marker:

1. Hover a mouse cursor on a marker
2. Press the *Delete* key

To link many of markers with another object:

1. Select the *Groups* mode
2. Hold-down LMB on a marker to link from
3. Move a mouse cursor on the object to link to
4. Release LMB

The link is represented by a blue line between the linked objects.

The hold-down *Shift* key + one-clicking LMB is used to add the markers to.

To remove a link between the objects:

1. Select the *Groups* mode
2. Hold-down LMB a marker you want to remove the link from
3. Hover mouse on the empty space on the map
4. Release LMB

If a object is linked with many of markers it will randomly place at the beginning of the mission at a one of the markers or its own position. This offers another way to create randomness at a mission start, with more precise control compared to using the unit's *Placement radius* setting.

NOTE:

- A marker used in this way will still be drawn on the map.
- A marker cannot be attached to the object created in the terrain editor (*Visitor*).

The *Insert/Edit marker* dialog box:

Name – this can contain a unique name of the marker. The marker names should comply with the rules of the variable naming (no spaces, no reserved characters, and no reserved words).

NOTE: In other editing modes the markers can only be found by recognizing their names.

Dialog Options:

- **Icon** – represents an opaque symbol on the map at a fixed scale
- **Rectangle** - represents the form of a pattern filled zone defined by the shape. The zone is displayed covering the same physical area.

- **Ellipse** –represents the form of a pattern filled zone defined by the shape. The zone is displayed covering the same physical area.

Color - defines the marker color. Dark gray color is by default.

Icon / Fill option:

- The **Icon** option is only available for an Icon marker.
NOTE: You can create *Icon* markers in-game by double-click LMB on the map within the *Diary*.
- The **Fill** option is only available for the *Rectangle* or *Ellipse* markers. The shape will be filled with the selected pattern. The fill patterns are slightly transparent.

Axis a / Axis b - these fields define the scale at which the marker will be drawn.

The icon markers have relative size, but rather display at a constant size irrespective of the map zoom. The axis values define the relative scale for the icon.

For example, marker with an axis value of 10 will be displayed 10 times larger than the default size of the icon display.

The zone markers have absolute size, in meters:

- *Axis "a"* presents east-west direction while angle has the value of "0"
- *Axis "b"* presents north-south direction while angle has the value of "0"

NOTE: To hide a marker set both axes to 0.

Angle - self-explanatory

NOTE: A marker can be rotated as a unit or a trigger.

Text - the colored text at the right from the marker (irrespective of the marker angle).

1.10 Modules

Modules are the *Game Logic* interfaces (introduced in *ArMA 2*).

They run the scripts from the game default setup.

To add module:

1. Select the *Modules* mode
2. Double-click LMB on the map

The *Modules* dialog box:

- **Unit** – self-explanatory
- **Name** – self-explanatory
- **Initialization** – self-explanatory
- **Description** – self-explanatory
- **Probability of presence** – self-explanatory
- **Condition of presence** – self-explanatory

A description of all the modules requires the text volume more than this manual. Therefore, this description here is not feasible and requires a separate manual. The some modules need to be described with the particular manuals.

1.11 Intel

To open the *Intel* dialog you need click LMB on the *INTEL* box.

The *Intel* dialog box:

- **Name** - the title of a mission or campaign will list for both the *Singleplayer* and *Multiplayer* game modes, and also in the *Diary*.
NOTE: If you do not name a mission, the name of the mission folder will be used.
- **Description** - The description is displayed in *Multiplayer* game mode.
NOTE: It is recommended to give a short description what the mission is about to identify it.
- **Date** - self-explanatory
- **Time** - self-explanatory

Weather – defines the initial weather.

NOTE:

- Setting the slider all to the right creates clear skies.
- Setting the slider all to the left creates a thunderstorm.

Fog - defines the initial fog density.

NOTE:

- Setting the slider all the way to the right creates maximum density.
- Setting the slider all the way to the left is no fog.

Forecasted weather - is defined by the same way above with a linear transition from the initial weather conditions to the forecast conditions occurring over the first 30 minutes after a mission began.

Forecasted fog - is defined by the same way above with a linear transition from the initial fog conditions to the forecast conditions occurring over the first 30 minutes after a mission began.

NOTE: The first 30 minutes after a mission began, the game engine carries out some long term the dynamic simulation of the weather, although it is over a timescale beyond most mission duration (changes occurring over 1.5 to 14 hours). For controlling the weather after the first 30 minutes you can use script.

Independents are friendly to - defines a side to which the *Independents* will be friendly during the mission.

NOTE: The *Civilian* side can inherit the same allies and enemies from *Independents*.

2. THE ADVANCED MODE (2D&3D)

To access the advanced mode of the mission editor:

1. In the *Main menu* screen, press the left *Alt/Ctrl + E* keys
2. Select a map from the *Select map* dialog box
3. Click the *Continue* button

2.1 Interface

The interface consists of three sections:

- the panel of the object hierarchy is placed on the left
- the workspace with a map is placed in the center
- the editing bar is placed on the right:
 - the *Intel* dialog box
 - the bar of the editing modes
 - the menu of the project management

To switch the view modes, press the *Edit in 3D world/Edit in 2D map* button.

NOTE: Pressing *M* key you can switch the *3D/2D view* modes too. If you preview scene you can press *Esc* to access *Paused* menu, in which both the *Edit in 2D map* and the *Edit in 3D world options* are available.

NOTE: The *Synchronization* button absents in the editing bar.

Camera controls

Keyboard	Mouse	Description
W	-	Forward move
S	-	Backward move
A	-	Left move
D	-	Right move
Q	or rotate Scroll wheel forward	Upward move
Z	or rotate Scroll wheel backward	Downward move
NOTE: You can increase / decrease the action speed by pressing the <i>Shift/Ctrl</i> with keys above.		
Numpad 8	-	Upward rotate
Numpad 2	-	Downward rotate
Numpad 4	-	Left rotate
Numpad 6	-	Right rotate
-	Hold down RMB + move mouse	Free view

TIP: To place the camera on a map in the *Edit in 2D map* mode:

- One-click RMB on the map where you want
- In the context menu select *Default camera*

2.2 Centers and Groups

Before creating a unit you need to create a *Center (Side)* and *Group* for it.

To create the *Center*:

1. Select the *Center* (F10).
2. Double-click LMB on the map.
3. In the *Object properties* dialog box, select a *Side* from *Side* menu.
NOTE: You can set *Friend state* each of four sides.
4. Click the *OK* button

To create the *Group*:

1. Select the *Group* mode (F2).
2. Double-click LMB on the map.
3. In the *Object properties* dialog box, click *OK* button.

NOTE: Units have their own groups. In single group might be one unit or more.

2.3 Unit

To create unit:

1. Select the *Unit* mode (F1).
2. Double-click LMB on the map.
3. In the *Object properties* dialog box, set up features of unit.
4. Click the *OK* button.

Creating of other objects is similar to those in the normal mode (2D).

2.4 Object Control

The control of selected object:

Keys	Mouse	Action
-	Hold down LMB + move mouse	Move
Alt +	Hold down LMB + move mouse forward/backward	Move upward/downward
Shift +	Hold down LMB + move mouse	Rotate
Ctrl + C	-	Copy
Ctrl + V	-	Paste

NOTE: Holding down *Shift* and clicking LMB on a unit or waypoint will not select all the objects associated with that unit's group as in the normal mode (2D).

2.5 HOW TO

How to use all the Arma 2 houses stuff:

1. Download *Jon-C5- Editor* to have easily access to all houses and other objects used in the Arma 2:
<http://www.armaholic.com/page.php?id=5932>
2. Install the file as mod.

NOTE: The add-ons are accessible in the both advanced (2D/3D) and normal (2D) mode.

How to export objects created in the advanced mode (2D/3D)

To use the objects for editing in the normal mode (2D) you can convert the ***.biedi** file to the ***.sqm** file.

You may use "3de_conv" utility: <http://armed-assault.de/news/biedi---sqm-converter.html>

Installation (for the Arma 2):

1. Unpack the archive.
2. Place the folder @ 3de_conv in %Installaion_path%\Arma 2
3. Register this folder as a mod (in the game label add-mod = @ 3de_conv). This will place the objects created in the advanced mode (2D/3D).

NOTE: Objects placed without this add-on, after conversion **BIEDI** to **SQM** format will not be in their positions in the normal mode (2D).

Usage:

1. Copy **mission.biedi** from your mission folder created in advanced mode (2D/3D) into **3de_conv** folder.
2. Drag **mission.biedi** on the icon **3de_conv.exe**. It will be creating **mission.sqm**.

NOTE: If mission.sqm already exists then this will be overwritten.

Conversion parameters:

- Intro - Convert as the entry of the mission
- Win - Convert a conclusion (win) mission
- Loose - Convert a conclusion (loss) mission

NOTE:

- You can apply only one of the parameters at time
- You can enter the parameters:
 - In the command prompt
 - In created shortcut

Example: In the converter shortcut, *Target* field: "C:\%your_path%\ 3de_conv.exe" intro

In this case:

- Create a shortcut to **3de_conv.exe** within folder *3de_conv*.
- Set a parameter in the shortcut.
- Drag **mission.biedi** on the shortcut.

2.6 Import of content from mission.sgf

The editor in the advanced mode (2D/3D) saves the content otherwise then in the normal mode (2D).

In this case, the project folder contains two files:

- mission.biedi
- mission.sgf

You have to create similar project with some distinct "tag" in normal mode (2D) to import here the content from project created in the advanced mode (2D/3D).

Importing the contents:

1. Copy **mission.sgf** into the project folder created in normal mode (2D)
2. Open the **mission.sgf** with a text editor
3. On top of the script delete the following:

```
activateAddons [  
];
```

```
activateAddons [];  
initAmbientLife;
```

4. Write instead:

```
setAccTime 0.0;
```

5. On bottom of the script delete the following:

```
runInitScript;  
finishMissionInit;
```

6. Write instead;

```
setAccTime 1;
```

7. Create init.sgf and write here:

```
If (isserver) then {execVM "mission.sgf"};
```

3. SCRIPTING

Creating a complex mission will require a scripting.

NOTE: The *Multiplayer* mission is much more complex. It is recommended that you created *Singleplayer* missions and scripts before creating *Multiplayer* missions.

Configuration and Function Viewing

It is possible to view configurations and functions in the mission editor. For this, you need to create three user missions:

1. Load a map you want
2. Create a basic project and save it as a user mission.

3. Create separately a supporting project to view configuration classes and functions, and save it as a user mission:
 - Create a player unit
 - Create *Functions* module. No synchronizing needed.
 - Create a trigger:
 - Set both Axis A and B to value of 0
 - Enter the code into *Condition* field:
!isnil "BIS_fnc_init"
 - Enter the code into *On Activation* field:
[] call BIS_fnc_configviewer (for configurations) / [] call BIS_fnc_help (for functions)

These projects allow you to switch between a viewing and working on the mission.

NOTE: The viewers will run when you open the supporting projects. To restart the viewers you have to restart those projects.

Debugging

You can use the option command **–showscripterrors** to see error messages:

1. Create the game shortcut on the *Desktop*.
2. One-click RMB on the shortcut.
3. In context menu, select the *Properties* item.
4. In the *Object* field, add the command:
"C:\Program Files\Bohemia Interactive\Arma 2\arma2.exe" **–showscripterrors**
5. Click the *Apply* button
6. Click the *OK* button.


Error Messages

Format

Error messages occur when the game engine loads the line of code but is unable to interpret the command. Error messages appear at the top of the screen when a mission starts. The message displays the basic information where the problem occurred. This is the location where the script stopped making sense to the game engine.

NOTE: The actual error may be on another line of code.

Example:



Message Types

- **Scalar bool array string OXE0FFFFFFF**

The nonexistent variable displayed by the command *format*:

```
_local_variable = 12;  
hint format ["%1", _loc_variable]; // Using a misspelled variable
```

```
1-1-A-1 1 (GunRunner): "SCALAR BOOL ARRAY STRING OXE0FFFFFFF"
```

- **Invalid number in expression**

The incomplete formula:

```
_newVar = 2 + ;
```

```
...VIEWSave.Intro\test.sqf  
newVar = 2 + |#|;  
Error Invalid number in expression  
File  
C:\Users\GunRunner\Documents\VBS2\mpmissions\  
tro\test.sqf, line 2
```

- **Generic error in expression**

The incorrect data type:

```
_vehicle setFuel "1"; // Using incorrect data type for numbers  
_variable = "string" + 42; // Using incorrect data types when using mathematics functions
```

```
...EWSave.Intro\test.sqf  
_var = "string" |#|+ 42;  
Error Generic error in expression  
File  
C:\Users\GunRunner\Documents\VBS2\mpmissions\  
tro\test.sqf, line 2
```

- **Type "something" expected "another"**

The unexpected data type:

```
"truck1" setFuel .5;
```

```
...tmpPREVIEWsave.Intro\test.sqf  
"truck1" |#|setFuel .5;  
Error setfuel: Type String, expected Object  
File  
C:\Users\GunRunner\Documents\VBS2\mpmissions\  
tro\test.sqf, line 1
```

- **Type string expected code**

Usually occurs with a block of code:

```
If (alive player) then {player setUnitPos "UP"};
```

```
...Wsave.Intro\test.sqf  
if(alive player) |#|then  
{  
player setUnitPo "UP";  
};  
Error then: Type String, expected Array, code  
File  
C:\Users\GunRunner\Documents\VBS2\mpmissions\  
tro\test.sqf, line 2
```

- **Zero divisor**

Trying to divide a number by zero or divide zero by a number. Can also occur with arrays

```
0/1 or 1/0
myValue = [1, 2, 3] select 4;
```

```
...ve.Intro\test.sqf"
myValue = [1, 2, 3] |#|select 15;
Error Zero divisor
File
C:\Users\GunRunner\Documents\VB52\mpmissions\
tro\test.sqf, line 2
```

- **Error missing }**

The game engine shows where the script stopped making sense.

NOTE: The actual error may be found above or below the line number.

```
If (alive player) then
{
player setUnitPos "DOWN"
;
```

```
...ntro\test.sqf"
if (alive player) then
{ |#|
player setUnitPos "down";
player sideC...
Error Missing }
File
C:\Users\GunRunner\Documents\VB52\mpmissions\
tro\test.sqf, line 33
```

Trouble Shooting Tips

- Work on one section at a time.
- Save working copies as you go.
- Output the debug messages of key variables in different parts of the script.
Use the command **str** to check the value of a single variable. If nothing is displayed on the screen, the variable does not have a value (a scalar error). Chances are the variable is misspelled somewhere.

```
player sideChat str _var1;
//advance scripting, see wiki for more information
hint format ["dir %1, dis %2", _var1, _var2];
player sideChat format ["dir %1, dis %2", _var1, _var2];
```

- Display messages when certain parts of the code are successful

```
player sideChat "reached section 1";
```

Release: 2014.07.19

Update: 2015.07.12

Publisher: <http://vied-arma.ucoz.com/>